

Previous RM-CG Firmware

version information

V2.8.0

Fixed bugs

- Fixed some minor bugs.

V2.5.0

New Functions

- The information displayed in the Web GUI “RM-CG Device Manager” can now be changed to one of multiple languages. Information files for multilingualization will be posted on the ADECIA website.
- When used with SWR2311-10P, the status of optimized Dante settings can now be displayed in the Web GUI “RM-CG Device Manager”.

V2.0.0

New Functions

- The ADECIA ceiling solution, consisting of RM-CG, RM-CR and VXL1-16P, has received Zoom certification.
- Added [Focus area] and [Exclusion area] selection settings to the tracking area for microphone sound pickup.
- Added Low latency mode to Ch2 signal processing.
- Supports IEEE802.1X for enhanced network security.
- Added Output Router for selecting the Dante output signal.
- Supports AES67.

Improvements

- The IP address for Dante can now be set from the Web GUI.
- Any file name (not just the MAC address) can now be used when importing configuration files with the Web GUI.
- Auto mixer Ch. 1/Ch. 2 can now be set individually.
- Dante Output Ch. 1/Ch. 2 can now be muted individually. In addition, a parameter to link with the LED display of the Mute status has been added.
- Solved other minor problems.

V1.7.0

Information

- These release notes accompany the version upgrade of ADECIA, one-stop sound solution for remote conferencing. There are no changes in functionality compared with V1.5.0.

V1.5.0

New Functions

- When RM-CG and RM-CR are used in combination, it is now possible to change the color of the front panel indicator of RM-CG when there is no call. RM-CR and the Web GUI "RM-CR Device Manager" are required to make this change.

Improvements

- Improved the operation of the microphone beam.
 - Increased the speaker tracking speed.
 - Effectively picks up soft voices but does not easily react to noises.
- Improved the operation of the echo canceller.

V1.2.0

New Functions

- Now supports SNMP (Simple Network Management Protocol), a remote management protocol.
- Added a mute group function to link microphone muting for each group. It can be used in an environment combined with the RM-CR.

Improvements

- Improved the description of the Web GUI.

V1.1.0

New Functions

- You can now check and change parameters for digital signal processing on the [Processing] window in Web GUI. You can also now import and export settings for digital signal processing on the [Configuration] window.
- Added a command for outputting the beam direction in the Remote Control Protocol.

Fixed Bugs

- Fixed the issue in which the Web GUI [SUBMIT] button cannot be clicked.
- Fixed other small issues.

V1.0.2

New Functions

When adjusting the effective range of RM-CG tracking in the Web GUI [MICROPHONE SETTINGS], you can now drag and drop the end points (4 orange dots) of each line displayed in the [Tracking area] diagram.